


Edraw Authorization Server V2.4.10 User Manual



1. Server Installation and Activation

1 Installation and Deployment

Edraw Authorization Server V 2.4.10 comes with advanced Docker technology, which simplifies the installation process and eliminates the impact of environmental differences on the servers.

It also has built-in mechanisms such as automatic service activity checks and the ability to troubleshoot problems.

It is strongly recommended to deploy this authorization server to Linux operating systems.

1.1 Linux Operating System

Linux server recommended configuration:

- Hardware: 4-core CPU, 2G memory, 50G hard disk (SSD recommended)
- Software: CentOS 7.8, Docker -CE 20.10+

1.1.1.X86 Architecture

Edraw Server Docker image download link:

<https://www.edrawsoft.cn/2download/edserver/edrawserver-2.4.10.tar>

The Linux system image download/import and start container commands are as follows:

```
# Enter the data directory based on your actual situation
$ cd /data/docker/edrawserver/
# Download image
$ wget https://www.edrawsoft.cn/2download/edserver/edrawserver-2.4.10.tar
# Import image
$ docker load -i edrawserver-2.4.10.tar
$ docker images
REPOSITORY                                TAG      IMAGE ID      CREATED        SIZE
docker.edrawsoft.cn/version/edrawserver  2.4.10   bbe8dec8db8b  About a minute ago  112MB
# Run docker
$ docker run -d --name edrawserver \
  --restart always \
  --privileged \
  -e TCP_SERVER_ADDR="Linux server public address:8915" \
  -e EDRAW_HTTP_BASE_URL="http://Linux server public address" \
  -p 80:80 \
  -p 8915:8915 \
  -v $(pwd)/data:/app/data \
  -v $(pwd)/log:/app/log \
  docker.edrawsoft.cn/version/edrawserver:2.4.10
$ docker ps
CONTAINER ID   IMAGE                                COMMAND                  C   S   PORTS          NAMES
d61455f2e590   .../edrawserver:2.4.10             "/bin/sh..."          ...  ...  0.0.0.0:80->80/tcp...  edrawserver
(For typesetting and highlighting key contents, some contents are replaced with "...")
```

1.1.2.ARM architecture

Edraw Server Docker image download link:

<https://www.edrawsoft.cn/2download/edserver/edrawserver-2.4.10-arm.tar>

The Linux system image download/import and start container commands are as follows:

```
# Enter the data directory based on your actual situation
$ cd /data/docker/edrawserver/
# Download image
$ wget https://www.edrawsoft.cn/2download/edserver/edrawserver-2.4.10-arm.tar
# Import image
$ docker load -i edrawserver-2.4.10-arm.tar
$ docker images
```

REPOSITORY	TAG	IMAGE ID	CREATED	SIZE
docker.edrawsoft.cn/version/edrawserver	2.4.10-arm	bbe8dec8db8b	About a minute ago	112MB

```
# Start container
$ docker run -d --name edrawserver \
    --restart always \
    --privileged \
    -e TCP_SERVER_ADDR="Linux server public address:8915" \
    -e EDRAW_HTTP_BASE_URL="http://Linux server public address" \
    -p 80:80 \
    -p 8915:8915 \
    -v $(pwd)/data:/app/data \
    -v $(pwd)/log:/app/log \
    docker.edrawsoft.cn/version/edrawserver:2.4.10-arm
$ docker ps
```

CONTAINER ID	IMAGE	COMMAND	C	S	PORTS	NAMES
d61455f2e590	.../edrawserver:2.4.10-arm	"/bin/sh..."	0.0.0.0:80->80/tcp...	edrawserver

(For typesetting and highlighting key contents, some contents are replaced with "...")



1.2 Windows Operating System

Edraw Server Zip package download link:


<https://www.edrawsoft.cn/2download/edserver/edrawserver-2.4.10.zip>

Installation Steps:


1. Download the Zip package and unzip it to the local disk. It is recommended to install it in the root directory of the drive, and there should be no spaces in the path, for example: C :\EdrawServer
2. Configure the environment variables TCP_SERVER_ADDR (client connection address, that is, the address where the client is able to access the server), EDRAW_HTTP_BASE_URL (the path to access the server, http://address). If the server address is 192.168.57.2, the configuration example is as follows:



3. Use "Explorer" to open the folder where the program is located. Right-click "Register_Start.bat", and select **"Run as administrator"**. (You also need to "Run as administrator" for Stop_Uninstall.bat).



- After installation is successful, it will be registered as a system service (It will run in the background and the system will start automatically once it launches), and automatically open the browser to jump to the system page thereafter.



```


C:\Windows\System32\cmd.exe
***** Generate config file *****
Done

***** Register system service *****
Installing service 'Edraw License Server (EdrawServer)'...
Service 'Edraw License Server (EdrawServer)' was installed successfully.
Done

***** Start EdrawServer *****
The Edraw License Server service is starting.
The Edraw License Server service was started successfully.
Done

Press any key to continue . . .
  
```

- In the "Services" tab of "Task Manager", you can see that EdrawServer has been registered as a system service





Name	PID	Description	Status	Group
Eaphost		Extensible Authentication Protocol	Stopped	netsvcs
edgeupdate		Microsoft Edge Update Service (edg...	Stopped	
edgeupdatem		Microsoft Edge Update Service (edg...	Stopped	
EdrawServer	9736	Edraw License Server	Running	
EFS		Encrypting File System (EFS)	Stopped	




2 Initial Activation

You are required to add a license to the Edraw Server before it can provide authorization services for client software such as Edraw Mind Map, Edraw Icon, and Edraw Project Management.

After the container is started, you will see the login page through `http://{ip}/`. Use `admin/12345678` to log in to the system, and the "Authorization Activation" window will pop up thereafter.





Click on the [Copy] button to copy the “feature code” and send it to the customer service staff to obtain the “authorization code”. Paste it into the “authorization code” text box and click the [Activate] button to complete the initial activation.



3 Password Change

Hover the mouse over [admin] in the upper right corner and click the pop-up menu [Change Password]. Enter your old password, followed by your new password. Repeat your new password, and then click OK.



4 Update Authorization

When the license is changed, you may click the [Update License Information] button on the [About] page, and the subsequent operations will be the same as the initial activation.

5 Disable/Enable the Client

Due to some unforeseen circumstances, it may be necessary to disable the registered client to release the license that was initially used for the client.

To do this, open the [User Information] interface, where the list of registered clients will be shown.

The query conditions will be divided into two groups according to "Disabled" and "Enabled" status. Enter the search content in the box to match the three fields of job number, name, and host name at the same time.

When the number of registered users is too high, fuzzy queries will occupy more computing resources. It is recommended to use "precise query" instead in this case, as it meets most application scenarios.

If you find a client in the "Enabled" state, you may click the [Disable] button to revoke their access, and a prompt will appear when the client logs in again to inform them that their access has been disabled; if you wish to provide access again to users in the "Disabled" status, you may click the [Enable] button to reinstate their access to the server.

The screenshot displays the 'Edraw Server' interface. On the left is a sidebar with navigation options: Overview, Device Management (selected), Upgrades, Configuration, and About. The main area shows the 'User Information' page. At the top, it indicates '*** Company' and 'Client Activation Address: 192.168.13.22:8915'. Below this are logos for Wondershare EdrawMind, EdrawMax, and EdrawProj, along with an 'Export to csv' button. A filter section includes radio buttons for 'Enabled' (selected) and 'Disabled', and another set for 'Exact Match' (selected) and 'Fuzzy Lookup'. A search bar is labeled 'Search (ID, Name or Host)'. The main content is a table with columns: User ID, User Name, OS Type, Category, Language, Version, Host Name, Status, and Manage. All clients listed have a status of 'Inactive'. At the bottom, there is a pagination bar showing 'Total 8 terms/page, Display 20 terms/page' and a 'Go to page' input field.

User ID	User Name	OS Type	Category	Language	Version	Host Name	Status	Manage
40bit①	yangyq	windows	common	multi	9.0.13	Win102021P...	Inactive	Disable
40bit	yangyq	windows	common	multi	9.0.11	Win102021P...	Inactive	Disable
2	2	windows	common	multi	9.0.12	SZ19063341...	Inactive	Disable
2	2	windows	common	multi	9.0.13	SZ19063341...	Inactive	Disable
ubuntu	ubuntu	ubuntu	common	multi	9.0.14	huhc-virtual-...	Inactive	Disable
1234556	yangyq	osx	common	multi	9.0.12	iMac.local	Inactive	Disable
centos	centos	centos	common	multi	9.0.14	localhost.loc...	Inactive	Disable
Mac	Mac	osx	common	multi	9.0.12	SZ19063341...	Inactive	Disable

6 Export Client Information

You may export all client information stored in the product by clicking on the [Export csv] button. It is recommended to use WPS or a newer version of Excel to open the file to avoid the problem of character set mismatch in the document.

The screenshot shows the Edraw Server web interface. On the left is a dark sidebar with navigation links: Overview, Device Management (highlighted), Upgrades, Configuration, and About. The main content area has a top header with '*** Company' and 'Client Activation Address: 192.168.13.22:8915'. Below this are three product logos: Wondershare EdrawMind, Wondershare EdrawMax, and Wondershare EdrawProj. A blue 'Export to csv' button is highlighted with a red box. To its right is a toggle switch set to 'Enabled'. Below the button is a table of client information. A red arrow points from the 'Export to csv' button to the table. At the bottom of the interface, a file download bar shows 'Master-20220811-....csv' with a download icon and an upward arrow.

User ID	User Name	OS Type	Category	Language
40bit①	yangyq	windows	common	multi
40bit	yangyq	windows	common	multi
2	2	windows	common	multi
2	2	windows	common	multi
ubuntu	ubuntu	ubuntu	common	multi
1234556	yangyq	osx	common	multi
centos	centos	centos	common	multi
Mac	Mac	osx	common	multi

Total 8 terms/page, Display 20 terms/page

Master-20220811-....csv

7 Client Automatic Upgrade

As the Edraw series software continues to upgrade interactively, in order to reduce the burden on administrators, the client versions after EdrawMax 11.1.3 and MindMaster 9.0.8 will support automatic update checks.

After the authorization server updates the new version information, the user will be prompted to upgrade and confirm the update automatically. The administrator will then obtain the upgrade package (in zip format).

Click on the [Upload] button on the [Upgrade Management] page to complete the upgrade package update . You may also click the [Delete] button to delete the upgrade package on the server.

Note:

1. Upgrading packages of the same category will retain only the last version of the server;
2. In order to avoid network congestion caused by a large number of user downloads, the server only allows 40 concurrent downloads by default.

Edraw Server

*** Company Client Activation Address: 192.168.13.22:8915

admin

Instructions:

1. The installation package is identified by four types of information: product, OS type, subclass, and language.
2. For the same type of installation package, the server only keeps the last uploaded version.
3. Only when the client with the upgrade function completely matches the four types of information will it be automatically installed the latest version or prompted to update.
4. You can choose to upload multiple installation packages at a time, but the total size cannot exceed 500M.

[Upload](#)

Product	OS Type	Subclass	Language	Version	Installation Package	
Pro	windows	common	cn	2.3.5	edrawpro_2.3.5_intranet.exe	Delete
Master	windows	common	multi	9.0.13	mindmaster-9.0.13-multi-binner.exe	Delete
Max	windows	common	cn	11.5.2	EdrawMax_11.5.2_cn_inner.exe	Delete

8 Broadcast Messages

The system reserves a broadcast message interface for broadcasting messages to Edraw software users. Fill in the [Global Configuration] [Broadcast Message] and the user will be prompted with this message the next time they open the server.

9 Server Migration

When the authorization server needs to be migrated, the address of the new server can be set on the old server, and the client will automatically switch to the new server after startup.

The screenshot displays the Edraw Server configuration interface. On the left is a dark sidebar with the following menu items: Overview, Device Management, Upgrades, Configuration (highlighted), and About. The main content area has a top header with '*** Company' and 'Client Activation Address: 192.168.13.22:8915'. In the top right corner, there is a globe icon and the text 'admin'. The main area contains two configuration sections:


- Notification:** (After configuration, a prompt message will pop up when a user starts software again.) This section includes a large text input field and two buttons: 'Clear' and 'Confirm'.
- Server transfer:** (After configuration, the authorization server address will be updated when a user starts software again.) This section includes a text input field with an example: 'For example: 192.168.1.1:8915; edrawserver.company.com: 8915', and two buttons: 'Clear' and 'Confirm'.

2. Client Product Activation

Take EdrawMax as an example to show the client product activation.


1. Activate with server

After installing the EdrawMax client, double-click the shortcut created on the desktop to start EdrawMax. An activation request will pop up automatically when you open it for the first time.




After the activation request appears, fill in the IP address, port, name and job number of the server to activate the product. (Note: the name and job number may be left blank, the default is "-").

For example: the server IP and port information are **IP: 1 0.10.7.162 port: 8 915**. Please fill in the information in the position where the activation prompt pops up on the EdrawMax client.




After filling in the IP address and port information, click on the “Activate” button below, and a prompt will appear if the activation is successful. Please restart EdrawMax to start using it.




If the activation fails, the following prompt will appear.

Should this happen to you, please contact IT or the server administrator to confirm whether the IP and port information are correct and whether the service has been started successfully.



If activation had been skipped during startup, you may use the Activation function under the Help function bar in the EdrawMax function page to activate the product.



2. Activate with your phone:

For customers who are unable to build an intranet authentication server, the mobile phone QR code activation method serves as an alternative for intranet activation.

Click on the [Help] menu of the software, and then click [Activation] → [Phone Activation].



A Wondershare Company



www.edrawsoft.com



support@edrawsoft.com



www.facebook.com/edrawsoft



www.linkedin.com/company/edrawsoft



www.twitter.com/edrawsoft



www.youtube.com/c/cutedrawedwin/videos



www.pinterest.com/edrawsoft/_created



www.instagram.com/wondershare_edrawsoft